

USER'S GUIDE FOR

Ultimate Voice Recorder Version 5.75.2

Product Overview

Ultimate Voice Recorder satisfies all your recording needs. It will let you record a voice memo or phone call anytime by simply pressing hotkeys of your own choices. Phone calls can also be recorded automatically based on your choices. You can browse, label, delete and transfer all the recorded memo and phone calls with ease. You can set up a one-day, daily or weekly voice reminder with a recorded memo. You can record arbitrarily long memo or conversations. The application will automatically stop recording once the storage space is low on your phone and never will fill up your phone! You can also specify a default email address or a default MMS number for automatic forwarding of recorded clips. Hotkeys work anytime, always!

Features

- ◆ Customizable hotkeys to start/stop recording and play back.
- ◆ Or simply press **abc/pen/ Dictaphone** key three times to start/stop recording. (On Nokia E61, press **Up Arrow key/shift** three times to start/stop recording.)
- ◆ Or simply press **PPT** key three times to start/stop recording.
- ◆ Support recording in both AMR and WAV formats
- ◆ Support recording to phone memory or directly to memory card.
- ◆ Optional automatic recording of phone calls. You can enable/disable this option through the application settings.
- ◆ Adjustable maximum recording length.
- ◆ Set up voice reminders (alarms) with recorded memos.
- ◆ Password protected.
- ◆ Operate in background mode or/and user interactive mode
- ◆ Automatic startup upon phone power on. You can enable/disable this through the application settings.
- ◆ Automatic restarting an interrupted recording, for example, caused by an incoming call. You can specify what the application should do in this situation through the application settings.
- ◆ Ask for your permission before saving a recorded clip if you like.
- ◆ Always ready to accept hotkeys
- ◆ Easy to manage/browse the details of all recorded clips such as caller id, duration, timestamp.
- ◆ Search recorded clip by label, phone number or person's name.
- ◆ Automatic stop recording when the storage space on your phone is low.
- ◆ Send the recorded clips to other phones or PC via Bluetooth, Infrared, MMS or email (if email service is supported).

- ♦ Automatic forwarding of recorded clips to a predefined email account or MMS number.
- ♦ Easy to retrieve the recorded voice clips using Nokia PC suite.
- ♦ Hide all recordings from other software on your phone.

The application requires registration after 7 days of trial period. Not all of the above features are supported during trial period.

System Requirement

Basic Requirements:

- ♦ S60 3rd edition phones. The Ultimate Voice Recorder 5.75.2 only supports S60 3rd edition phones such as N80, E61, N73 and so on.

Additional Requirements:

- ♦ A PC that can run Nokia PC suite if installing the application from a PC
- ♦ A PC or another phone that has Bluetooth supports if installing the application using Bluetooth from a PC/phone.
- ♦ A PC or another phone that has IR supports if installing the application using IR from a PC/phone.

Installing, upgrading, uninstalling Ultimate Voice Recorder

How to install the software

- ♦ Use Nokia PC suite to install the sis file to phone memory/memory card from a PC.
- ♦ Send the sis file to target phones by Bluetooth, Infrared from a PC or another phone, and continue the installation process on the phones when the transfer is completed.

How to uninstall the software

Launch the *App.Manager* application, scroll down to highlight the “Ultimate Voice Recorder”, and press “Options->Remove” to uninstall the software.

How to upgrade the software

Install the sis file containing updated software in one of the two ways as described in the above *How to install the software* section. Be aware if you have the version 3.01.1 of the software, then you have to uninstall the version 3.01.1 before installing this version. If you perform un-installation of the old software first, then all the previously recorded clips and user preferences(settings) will be deleted during the process.

How to register the software

1. The software requires a registration key to unlock its full feature set.
2. The software expires in 7 days without registration.
3. Open the Ultimate Voice Recorder application from phone menu, and press

"Options->Register" to input the registration key.

4. Please contact us at support@ultimateportable.com for the registration key or contact the distributor/reseller of the software where you made your purchase for the registration key.

Using Ultimate Voice Recorder

- ◆ Upon successful installation, launch the application, then a "tape" icon appears on the bottom middle of your phone screen, then you can set up your preferences by pressing "Options->Settings". You can start recording by press "Options->record new clip" or press "Hide" to let the application go background and use hotkeys to trigger recording. You can choose to hide the icon by pressing "Options->Settings", and change "Hidden mode" to "Always" or "When Idle".
- ◆ Press hotkeys anytime to record, stop, pause and play.
- ◆ Default hotkeys to record, stop, play and pause are "#0", "#7", "#1" and "#8". You may change the hotkeys by pressing "Options->Settings" and change corresponding setting items. The hotkeys should not be longer than 7 digits.
- ◆ Or press *abc/pen* three times to start/stop recording. On Nokia E61, press Up Arrow key three times to start/stop recording.
- ◆ Or press *PPT* three times to start/stop recording.
- ◆ Or press "Options->Record new clip" to start recording.
- ◆ Use navigation key to locate the recorded clip in the gallery view, and press "Options->Open" or press navigation key to open the control view and play back the selected clip.
- ◆ In the control view, you can record, play, pause, resume, fast forward, and fast rewind a clip.
- ◆ The application consists of two parts: a background server responsible for recording and a gui for managing settings and recorded clips. You can specify whether only background server runs all the time or both parts runs all the time after you press "Hide" by adjusting "Run in background" option in Options->Settings.
- ◆ After you have launched the application from phone menu, press "Hide" to let the application go background, then you can control the starting/stopping of recordings by hotkeys, or *abc/pen/PPT* keys.(or Up Arrow key on Nokia E61)
- ◆ When the application is running in background, open the application from phone menu and press "Options->Exit" to close the application. Please be aware that once closed this way, the application has exited totally and will not perform any more recordings.
- ◆ Press "Options->Settings", scroll down to the bottom, and enable or disable "Auto start" according to your need. If "Auto start" is set to "Enabled", the application will start up automatically upon phone power up. Be aware that by default, "Auto start" is disabled!.

- ◆ Press “Options->Settings” and change “Recording limit” as you need. If the limit is set to be bigger than 10000 minutes, then it’s treated as unlimited recording.
- ◆ Set “Recording limit” to 0 if you need unlimited length recording. The actual recording length depends on the free storage space.
- ◆ Press "Options->Settings", and scroll down to turn on "Ask before saving" if you need the confirmation before the application saves a recorded clip. The option is turn off by default.
- ◆ To automatically record phone calls, press "Options->Settings", and set "Automatic mode" to "on", then all the calls will be recorded automatically. Also set the "Recording limit" to 0 so that the whole call will be recorded.
- ◆ Press "Options->Settings", and turn "Warning beep" on/off according to your needs. When it's off, no beep during call recording.
- ◆ Press "Options->Settings" to adjust how to handle interrupted recordings - you can specify the software to automatically restart the recording, or to prompt a message asking your permissions.
- ◆ Use left/right key to mark multiple clips for deleting or sending to other devices.
- ◆ Open Ultimate Voice Recorder and press "Options->Settings" to change hotkeys and other options such as recording limit, recording format, automatic recording of phone calls, automatic deletion of clips.
- ◆ After your phone powers up, wait until the tape icon appears on the bottom of the phone before using hotkeys! If no tape icon appears after a few minutes, launch Ultimate Voice Recorder manually and press “Hide” to let it run in background. (If you set “Hidden mode” to “Always” or “When idle”, then no tape icon appears.)
- ◆ You can also run Ultimate Voice Recorder in foreground to perform recording and playbacks. Press “Options->record new clip” to record, for example.
- ◆ Open Ultimate Voice Recorder to browse and edit all the recorded memo and phone call clips.
- ◆ Press "Options->Settings" to adjust “Hidden mode” to specify when to show the tape icon - always, never or only while idle.
- ◆ Press “Options->Settings” to specify whether and when a recorded clip should be deleted after being transferred to other devices.
- ◆ Press “Options->Settings” to specify the default email address you want to use when transferring clips by emails.
- ◆ Press “Options->Settings” to specify the default MMS number you want to use when transferring clips by MMS.
- ◆ To use Nokia PC suite software to copy recorded clips to your PC, open the "c:\Data\UltimateVR" and "e:\Data\UltimateVR" directories on your phone in the file explorer of the PC suite. All the recorded clips are in those two directories.

- ◆ Each time you want to send out recorded clips by MMS or email, the application will ask for your permission first by presenting a dialog to you. Press “yes” to let the application proceed. You can modify this behavior by pressing “Options->Settings” and changing “Prompt for billable events”.
- ◆ Open the application from phone menu, and press “Options->Register” to input your registration key and unlock all the features of the application.
- ◆ Don't use Nokia PC suite software to delete recorded clips on your phone, use Ultimate Voice Recorder to do so instead.
- ◆ Press “Options->Hide recordings” to prevent other software from seeing your recorded clips. Be aware that if you do so, then even Nokia PC suite won't be able to see the recordings. If you want to copy recordings using Nokia PC suite, please press “Options->Unhide recordings” first.
- ◆ Press “Options->Search” to perform a search on label, phone number or person's name associated with recorded clips.

Configurable Settings

Storage option: specify the location (phone memory or memory card) to store recorded clips.

Call recording format: specifies what format to use for recording calls. AMR and WAV formats are currently supported.

Memo recording format: specifies what format to use for recording voice memos. AMR and WAV formats are currently supported.

Recording limit: the maximum recording length of each clip. If “No limit” is chosen, the length of the clip being recorded depends on the free space of the chosen storage. The application will not fill up the storage space and will stop recording automatically if the storage space is low.

Automatic mode: if on, starts recording automatically when a call is connected, and stops recording when the call is terminated.

Warning beep: if on, a beep tone will be heard during recording a conversation.

Record code: the key sequence to start/resume recording at anytime.

Playback code: the key sequence to play back the last recorded clip.

Stop code: the key sequence to stop recording/playback.

Pause code: the key sequence to pause Recording/playback.

Use hotkeys: specify whether the key sequence for recording, playback, stop, and pause should be enabled, and whether only abc/Pen/Dictaphone key is enabled.

Auto delete time: specifies whether to have a recorded clip deleted automatically after it has been reviewed(listened) or transferred to other devices via Bluetooth, IrDA, MMS or email and when it should be deleted.

Auto delete type: specifies whether to delete all recordings based on “Auto delete time” or only delete those that have been sent out/ transferred to other devices via Bluetooth, IrDA, MMS or email and when it should be deleted.

Default email: specifies the default email address to use when you want to send a clip by email.

Default MMS: specifies the default MMS number to use when you want to send a clip by MMS

Auto send: specifies whether to forward the recorded clips to the default email or default MMS after recordings finish.

Hidden mode: if set as “always”, no tape icon will appear on the phone screen. Be aware that in this mode, you will not have any visual indicator of the operations going on. If set as “when idle”, then the icon only appears during recording or playing back.

Interrupted recording: specifies how to proceed if a recording is interrupted. If “Auto resume”, then the recording will resume automatically in about one second; if “Prompt”, then a message will pop up to ask you what to do; if “Cancel”, then the recording will stop, no extra steps are taken.

Auto start: if enabled, the application will start automatically upon phone power-up and be ready to accept hotkeys.

Ask before saving: if on, the application will ask you whether to save a recorded clip or not after the recording is finished.

Gallery password: if set, the application will ask for password each time when you try to play back a recorded clip from the gallery view.

Prompt for billable events: if yes, the application will ask for your permission each time you want to send recorded clips via email and MMS. You will be always asked upon the first time you use email or MMS.

Run in background: if yes, only background server remains running in the background all the time for recording purpose after you press “Hide” or after some idle time period of your phone. If no, the gui part of the application will also run all the time and can be visible in task list.

Legal Notice

Please note that while the application supports recordings of phone calls, it is not legal to do so in some countries or regions and it may be required to let the other party know recordings are going on if you choose to record (for example, turn on “Warning beep” in settings). Please use the software in accordance with the laws and regulations in your region. We shall not be responsible for any legal issues incurred!